

# PHONE COIN



## MASTERNODE GUIDE

<https://phonecoin.space>


# Set Up Phone Coin Masternode Hot and cold wallet

\*This Guide only from new install VPS\*

## ➤ Setup Windows Wallet

### ○ Download Windows Wallet and Send Collateral Coin

- Download wallet from <https://phonecoin.space> and Run the phonecoin-qt.exe
- Go to File - Receiving Address
- Click +New and Fill Label=MNT1 Then OK
- Right Click and copy address
- Sent Collateral Coin to That Address
- Wait the Collateral to Minimum 25 confirmation



## ➤ Setup VPS

### ○ Register and Sign in to Vultr <https://www.vultr.com>

- Go to Page: <https://my.vultr.com/deploy/>
- Select Location
- Select Server Type: Ubuntu 16.04
- Select Size: \$5/Month
- Type Host Name, Server Qty and Deploy now
- Wait Notification for IP Address, User and Password


8 Server Hostname & Label

Enter Server Hostname

Servers Qty:  Summary: \$10.00/mo (\$200.00/yr)

## ➤ SetupUBUNTU 16.0


- Download Putty <https://www.putty.org>



- Type ip address to putty window - Host Name and click open
- Fill that user and password to putty

- Download and install PHONinstall.sh at ubuntu 16.04

```
rm phoneinstall.sh
wget https://phonecoin.space/PHONinstall.sh
chmod +x PHONinstall.sh
./PHONinstall.sh
```



- Save MASTERNODE\_GENKEY to notepad
- Save MASTERNODE\_VPS\_IP:PORT to notepad
- Check the latest block  
phonecoin-cli getblockcount
- If Still not synchronize do this step :  
systemctl stop phonecoin.service  
phonecoind -resync &  
phonecoin-cli stop  
systemctl start phonecoin.service  
phonecoin-cli getblockcount

## ➤ Back To windows

- Check Collateral Confirmation (Min 25 Confirmation)
- Get txhash and outputidx from masternode collateral
  - Go to Tools , debug console and type:  
masternode outputs
  - Save that <txhash> and <outputidx>

## ➤ Setup Masternode.conf at Windows

- Go Tools > open masternode configuration file
  - Add new line and write  
<MN\_NAME> <IP\_ADDRESS>:<PORT> <MASTERNODE\_GENKEY> <txhash> <outputidx>
  - Sample:  
MNT1 11.58.333.444:12222 PHONsdgfd354dvgbdsaf Pef4sdfsdrnj789sdf 0

## ➤ Setup Coin.conf

- Go Tools > open wallet configuration file
  - Add this line and save  
rpcuser=coinrpc\_user  
rpcpassword=coinrpc\_pass  
rpcport=12221  
port=12222  
rpcallowip=127.0.0.1  
daemon=1  
listen=1  
server=1  
externalip=VPS\_ip:12222  
#externalip=VPS2\_ip:12222  
#for 2nd vps / MN  
#externalip=VPS3\_ip:12222  
#for 3rd MN ....etc

- Exit wallet and open Wallet again

## ➤ Start Masternode

- Open Wallet>MasternodesIcon>MyMasternodes>Select MN and Start alias
- Check Masternode Status at ubuntu
  - Go back Putty - UBUNTU  
phonecoin-cli masternode status